

Mindsensor's Toolkit for LabVIEW for LEGO MINDSTORMS 2010


Version 2.02

10/16/2012


(For latest version, please contact support@mindsensors.com)

Adding Mindsensor's Palette

1. Create a folder "MindSensors" under `..\<labview>\vi.lib\NXT\MindSensors`
2. Copy the contents of folder "MindSensors Palette" from the toolkit to the aforementioned folder




3. Copy the "MindSensors.mnu" file from the toolkit to `..\<labview>\menus\Categories\NXT Robotics_3rd Party Sensors`
4. In LabView, the palette will appear under:
NXT Robotics →
NXT I/O →
Additional Sensors and Motors →
Mind Sensors



Adding Mindsensors Products to LVLM Schematic Editor

1. Copy the contents from the holder "Mindsensors Schematic" to
 ..\<labview>\Targets\ NI\NXT\ NXTToolkit\Schematic Editor\Nodes\NXT



2. Open Schematic Editor and check out the palette. Your palette should have mindsensor's product icons as highlighted in picture below.

